


Configure DNS Settings




For supported software information, click <u>here</u>.

To configure DNS settings on the Director node:

- 1. In Director view, select the Administration tab in the top menu bar.
- 2. Select System > DNS in the left menu bar.



3. Click the Add icon. In the Edit DNS popup window, enter information for the following fields.



Field	Description
Name Servers	Select the DNS name server.
Search Domain	Select the domain to search.
Local Domain	Enter the IP address of the local domain.

4. Click OK.

Supported Software Information

Releases 20.2 and later support all content described in this article.

Additional Information

Configure DNS Proxy
Configure DNS Servers