

# Create a New Site




For supported software information, click here.

This article describes how to create a site manually and by importing a CSV file that contains the site configuration information.

#### Create a Site

#### To create a site:

1. In the left menu bar, select Deploy. The main panel displays all existing sites.



2. Click the + Add Site icon. In the Create Site screen, enter information for the following fields.

	Create Site	
Name		
Region		
Default	~	
Address		
City		
State		
Country		
Zip Code		
Director		
Director-160	~	
Controllers		
Select Controllers		
Cancel		Save

Field	Description
Name (Required)	Enter a name for the site.
Region (Required)	(For Releases 10.2.1 and later.) Select a region.
Address	Enter a street address for the site.
City	Enter the name of the city where the site is located.
State	Enter the name of the state where the site is located.
Country (Required)	Enter the name of the country where the site is

Field	Description
	located.
Zip Code	Enter the postal code for the site.
Director (Required)	Select the Director node to manage the site
Controllers	Select a controller or hub controller node.

3. Click Save.

## Import a CSV File To Create Sites and Appliances


For Releases 11.4.1 and later.

To create one or more site at the same time, you can create a CSV file that contains the configuration information for the sites, and then you import the file to Concerto.

You can select a profile to use for the CSV file that is preconfigured with the columns to create a new site. After you download the new site CSV file, upload the CSV file to create new sites and appliances in bulk. Browse the file and upload for creating new sites and appliances. After the file is uploaded, check the Task page to see the progress of the site creation.

To download and upload the CSV file to create new sites:


1. In the left menu bar, select Deploy, and then click the  $lap{Download CSV}$  icon in the main panel.




https://docs.versa-networks.com/Secure\_SD-WAN/02\_Configuration\_from\_Concerto/Secure\_SD-WAN\_Configuration/Create... Updated: Wed, 23 Oct 2024 08:03:58 GMT

Copyright © 2024, Versa Networks, Inc.


2. In the Download New Site CSV screen, select the master profile to use for the CSV file download, and then click Download. Use the Search box to search for the profile name.




3. Save the downloaded CSV file to the local disk. The filename format must be *tenant-name##*(BASIC | STANDARD)##*master-profile-name.vversion-number.*csv. For example, VERSA##BASIC##Default-Active-Active.v1.csv.




4. Open the downloaded CSV file, add bind data for the sites and appliances, and then save the file.




5. To import the saved CSV file, click the Limport CSV icon in the main panel.




6. In the Upload Site CSV screen, click Browse, and then select the CSV file from local disk to upload.



7. Click Upload.



8. After CSV file has been uploaded, click the icon in the top menu bar to view the status of the create of sites and appliances.



# **Supported Software Information**

Releases 10.1.1 and later support all content described in this article, except:

• Release 11.4.1 supports downloading a CSV file to create sites and appliances.

### **Additional Information**

Concerto Home Screen Overview
Configure Regions